

Advanced Operating Systems

Side-Channels

Marcus Hähnel (marcus.haehnel@kernkonzept.com)

2026-07-06



What is a Side-Channel?



What is a Side-Channel?



Visual side-channel

Which call has a positive connotation?

Definition

Side-Channel

A side-channel is an *unintended* information source which enables the *extraction* of information that is processed through a means of communication or computation.

Definition

Side-Channel

A side-channel is an *unintended* information source which enables the *extraction* of information that is processed through a means of communication or computation.

Phone example

Primary source Audio signal

Unintended source Visual information
(e.g. facial expression, lip movement)

2001: A Space Odysee — Video

Covert channels?

Covert channels?

Definition: Side-Channel

A side-channel is an *unintended* information source which enables the *extraction* of information that is processed through a means of communication or computation.

Covert channels?

Definition: Side-Channel

A side-channel is an *unintended* information source which enables the *extraction* of information that is processed through a means of communication or computation.

Definition: Covert-Channel

A covert-channel is an *unintended* means of communication between two cooperating programs or systems.

Side-Channel usage

Side-Channel usage

Malicious

Extracting ...

- ... other customers data across virtual machines

Side-Channel usage

Malicious

Extracting ...

- ... other customers data across virtual machines
- ... crypto keys from applications in different address spaces

Side-Channel usage

Malicious

Extracting ...

- ... other customers data across virtual machines
- ... crypto keys from applications in different address spaces
- ... data from inaccessible processors

Side-Channel usage

Malicious

Extracting ...

- ... other customers data across virtual machines
- ... crypto keys from applications in different address spaces
- ... data from inaccessible processors

Benign

- ... detecting rootkits

Side-Channel usage

Malicious

Extracting ...

- ... other customers data across virtual machines
- ... crypto keys from applications in different address spaces
- ... data from inaccessible processors

Benign

- ... detecting rootkits
- ... detecting hardware trojans

Typical Side-Channels

Typical Side-Channels

What is a suitable side-channel

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)
- Error behavior (Out of memory? No more file handles?)

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)
- Error behavior (Out of memory? No more file handles?)
- Microarchitectural state

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)
- Error behavior (Out of memory? No more file handles?)
- Microarchitectural state
- Power usage

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)
- Error behavior (Out of memory? No more file handles?)
- Microarchitectural state
- Power usage
- Radiation (Heat, EM-Radiation)

Typical Side-Channels

What is a suitable side-channel

Any measureable parameter of the system and of its individual operations that changes depending on the processed data.

Example parameters

- Time (Duration)
- Error behavior (Out of memory? No more file handles?)
- Microarchitectural state
- Power usage
- Radiation (Heat, EM-Radiation)
- Unexpected persistence of data (Cold-boot, memory re-use)

Timing Channels



Attack vector

The duration of an attacker observable operation depends on the data processed by the victim

Timing Channels



Attack vector

The duration of an attacker observable operation depends on the data processed by the victim

Example - Graphics Processing

Holidays
Day 1

Timing Channels




Attack vector

The duration of an attacker observable operation depends on the data processed by the victim

Example - Graphics Processing

Holidays
Day 1



Timing Channels




Attack vector

The duration of an attacker observable operation depends on the data processed by the victim


Example - Graphics Processing

Holidays
Day 1




Convert to png: 1 s vs. 17 s

Cache Side-Channel



Cache Side-Channel



Level	Size	Cycles
L1D	32 KiB	4
L1I	32 KiB	4
L2	256 KiB	12
L3	3 MiB	36
DRAM	large	250

Prime & Probe

Concept

- Fill cache with known data (Prime)
- Repeatedly measure how long it takes to access this data
- Longer duration means cache-line was "stolen"

Prime & Probe

Example (Victim)

```
struct Person {  
    char name[56];  
    double account;  
} Alice, Bob;  
  
void transact(Person& p) {  
    p.account += 4000;  
}  
  
transact(Alice);
```

L1D 8-way set cache

Tag (20)	Set Index (6)	Offset (6)
(Alice)	0	56
(Bob)	1	56

Prime & Probe


Example (Victim)

```
struct Person {  
    char name[56];  
    double account;  
} Alice, Bob;
```

L1D 8-way set cache

Tag (20)	Set Index (6)	Offset (6)
(Alice)	0	56
(Bob)	1	56

Attacker



Prime & Probe

Example (Victim)


```
struct Person {  
    char name[56];  
    double account;  
} Alice, Bob;
```

L1D 8-way set cache

Tag (20)	Set Index (6)	Offset (6)
(Alice)	0	56
(Bob)	1	56

Attacker

Prime



Prime & Probe

Example (Victim)


```
struct Person {
  char name[56];
  double account;
} Alice, Bob;
```

L1D 8-way set cache

Tag (20)	Set Index (6)	Offset (6)
(Alice)	0	56
(Bob)	1	56

Attacker

Prime, Probe



Prime & Probe

Example (Victim)


```
struct Person {
    char name[56];
    double account;
} Alice, Bob;
```


L1D 8-way set cache

Tag (20)	Set Index (6)	Offset (6)
(Alice)	0	56
(Bob)	1	56

Attacker

Prime, Probe, Detect





Results of prime-probe observations for 20 distinct processed text words (rows). Darker fields indicate more evicted ways within an 8-way associativity set. Vertical lines identify cache addresses evicted in every observation.

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control
- Evict cache (by filling with known data)

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control
- Evict cache (by filling with known data)
- Run victim and measure runtime

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control
- Evict cache (by filling with known data)
- Run victim and measure runtime
- Evict most of the cache

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control
- Evict cache (by filling with known data)
- Run victim and measure runtime
- Evict most of the cache
- Run victim again and measure time

Evict & Time

Prime & Probe shortcomings

- Hard with smart caches
- Probing is prone to many false positives

Alternative: Evict & Time

- Possible if execution of victim code is under attacker control
- Evict cache (by filling with known data)
- Run victim and measure runtime
- Evict most of the cache
- Run victim again and measure time
- Time difference tells if victim used non-evicted cache-line

Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.

Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.



Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.



Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.



Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.



Challenges

Smart Caches

Smart Caches "reserve" parts of the L3 cache for individual cores. This makes priming hard.

Prefetchers

Detect access patterns. Probing may cause prefetch of evicted line leading to false-negative.

Scheduling

May evict primed data leading to 'blind times'

Pagefault Side-Channel

Assumption

Removing the OS from the TCB

Pagefault Side-Channel

Assumption

Removing the OS from the TCB

Scenario: Shielding Systems

- InkTag: Hypervisor / paging based isolation between OS and Application

Pagefault Side-Channel

Assumption

Removing the OS from the TCB

Scenario: Shielding Systems

- InkTag: Hypervisor / paging based isolation between OS and Application
- Intel SGX: Hardware-based isolation through read-protected memory

Pagefault Side-Channel

Assumption

Removing the OS from the TCB

Scenario: Shielding Systems

- InkTag: Hypervisor / paging based isolation between OS and Application
- Intel SGX: Hardware-based isolation through read-protected memory

Vulnerability

- These systems don't trust OS but use it to configure hardware
- OS makes a powerful adversary

Controlled Channel Attacks

First attack vector against Intel SGX

Controlled-Channel Attacks: Deterministic Side Channels for Untrusted Operating Systems

Yuanzhong Xu, Weidong Cui, and Marcus Peinado, MSR

System Model

- OS cannot directly observe memory or registers of application
- OS controls virtual memory

Example: string length

Example (Source, simplified)

```
//str on heap  
int strlen(char* str) {  
    int len = 0; //Stack  
    while (*(str++) != '\0')  
        len++;  
    return len;  
}
```

- Heap not present

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	0
Stack	...	...	0

Attackers Knowledge

Length = 0

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
! Heap	...	...	0
Stack	...	...	0

Attackers Knowledge

Length = 0

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	1
Stack	...	...	0

Attackers Knowledge

Length = 0

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	1
! Stack	...	...	0

Attackers Knowledge

Length = 1

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	0
Stack	...	...	1

Attackers Knowledge

Length = 1

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
! Heap	...	...	0
Stack	...	...	1

Attackers Knowledge

Length = 1

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	1
Stack	...	...	0

Attackers Knowledge

Length = 1

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	1
! Stack	...	...	0

Attackers Knowledge

Length = 2

Example: string length

Example (Source, simplified)

```
//str on heap
int strlen(char* str) {
    int len = 0; //Stack
    while (*(str++) != '\0')
        len++;
    return len;
}
```

- Heap not present
- Stack not present

	Phys-Addr	other Flags	P
Heap	...	...	0
Stack	...	...	1


Attackers Knowledge

Length = 2


Example Results (PF vs. Cache Channel)



Example Results (PF vs. Cache Channel)



Example Results (PF vs. Cache Channel)



Microarchitectural Channels




Meltdown

Leaking speculative CPU-state
to attackers

Moritz Lipp, Michael Schwarz,
Daniel Gruss, Thomas Prescher,
Werner Haas, Stefan Mangard,
Paul Kocher, Daniel Genkin, Yuval
Yarom, Mike Hamburg

Examples and figures taken from
the Meltdown paper



Spectre

Side-Effects of Out-of-Order execution


Toy Example

```
raise_exception();  
// the line below is never reached  
access(probe_array[data*4096]);
```

Side-Effects of Out-of-Order execution

Toy Example


```
raise_exception();  
// the line below is never reached  
access(probe_array[data*4096]);
```



Side-Effects of Out-of-Order execution

Toy Example

```
raise_exception();  
// the line below is never reached  
access(probe_array[data*4096]);
```



Constraints

- Raising the exception should be slow
- Accessing the array should be fast

Meltdown example code

```
; rcx = kernel address  
; rbx = probe array  
retry:  
    MOV AL, byte [RCX]  
    SHL RAX, 12  
    JZ retry  
MOV RBX, qword [RBX + RAX]
```

Power channels

Features

- Requires no capability to run code
- Hard to detect
- In theory usable remotely

Power channels

Features

- Requires no capability to run code
- Hard to detect
- In theory usable remotely

Requirements

- (very) high-resolution power measurement
- physical access to power supply
- detailed knowledge about exact processor used

Example


Example (Square-And-Multiply)

```
int exp(int base, int e) {  
    int res = 1;  
    while (e != 0) {  
        res *= res; //square  
        if (e & 1) res *= base; //multiply  
        e >>= 1;  
    }  
    return res;  
}
```

Example

Example (Square-And-Multiply)

```
int exp(int base, int e) {  
    int res = 1;  
    while (e != 0) {  
        res *= res; //square  
        if (e & 1) res *= base; //multiply  
        e >>= 1;  
    }  
    return res;  
}
```



Source: https://commons.wikimedia.org/wiki/File:Power_attack.png

Acoustic channels

Features

- Requires no capability to run code
- Hard to detect
- Usable remotely, bugs

Acoustic channels

Features

- Requires no capability to run code
- Hard to detect
- Usable remotely, bugs

Requirements

- Good audio equipment
- Reliable audio filters
- Knowledge about typing style
- Knowledge about hardware used

Example

Password typing attack

Keyboard Acoustic Emanations Revisited
Li Zhuang, Feng Zhou, J. D. Tygar
University of California, Berkeley


Example

Password typing attack

Keyboard Acoustic Emanations Revisited

Li Zhuang, Feng Zhou, J. D. Tygar

University of California, Berkeley





Example

Password typing attack


Keyboard Acoustic Emanations Revisited

Li Zhuang, Feng Zhou, J. D. Tygar



University of California, Berkeley



Results



Results



Electro Magnetic (EM) Radiation

Features

- Requires no capability to run code
- Hard to detect
- No "wire-cutting" needed

Electro Magnetic (EM) Radiation

Features

- Requires no capability to run code
- Hard to detect
- No "wire-cutting" needed

Requirements

- Expensive detection equipment (antenna, scope)
- Detailed knowledge about hardware used

Data Remanence

Warning

- NOT a classical side-channel
- no indirect observance of data → direct

Data Remanence

Warning

- NOT a classical side-channel
- no indirect observance of data → direct
- is still interesting

Data Remanence

Warning

- NOT a classical side-channel
- no indirect observance of data → direct
- is still interesting

Features

- Access to data you thought is gone
- Usually if you get data it is pretty good

Examples / Software

Example (Your friend, the compiler)

```
void secret() {  
    char* buf = (char*)malloc(1024);  
    // put sth. secret into buf  
  
    free(buf);  
}
```

Examples / Software

Example (Your friend, the compiler)

```
void secret() {  
    char* buf = (char*)malloc(1024);  
    // put sth. secret into buf  
  
    free(buf);  
}
```

Problem

?

Examples / Software

Example (Your friend, the compiler)

```
void secret() {  
    char* buf = (char*)malloc(1024);  
    // put sth. secret into buf  
    memset(buf, '\0', 1024);  
    free(buf);  
}
```

Problem

What if someone gets the same memory?

Examples / Software

Example (Your friend, the compiler)

```
void secret() {  
    char* buf = (char*)malloc(1024);  
    // put sth. secret into buf  
    memset(buf, '\0', 1024);  
    free(buf);  
}
```

Problem

?

Examples / Software

Example (Your friend, the compiler)

```
void secret() {  
    char* buf = (char*)malloc(1024);  
    // put sth. secret into buf  
    memset(buf, '\0', 1024);  
    free(buf);  
}
```

Problem

The compiler could optimize the memset out

Cold Boot

Lest We Remember: Cold Boot Attacks on Encryption Keys

J. Alex Halderman, Seth D. Schoen, Nadia Heninger, William Clarkson, William Paul, Joseph A. Calandrino, Ariel J. Feldman, Jacob Appelbaum, and Edward W. Felten
Princeton University, Electronic Frontier Foundation, Wind River Systems




Performance

	Seconds w/o power	Error % at operating temp.	Error % at -50 °C
A	60	41	(no errors)
	300	50	0.000095
B	360	50	(no errors)
	600	50	0.000036
C	120	41	0.00105
	360	42	0.00144
D	40	50	0.025
	80	50	0.18

Performance

	Seconds w/o power	Error % at operating temp.	Error % at -50 °C
A	60	41	(no errors)
	300	50	0.000095
B	360	50	(no errors)
	600	50	0.000036
C	120	41	0.00105
	360	42	0.00144
D	40	50	0.025
	80	50	0.18



Results




Image after 5, 30, 60 and 300 seconds

Defense mechanisms

Approach

Make all behavior that is observable independent of the input data

Defense mechanisms

Approach

Make all behavior that is observable independent of the input data

Caveat

Complete independence is not always achievable
(Algorithmic requirements, some channels hard to control)

Defense mechanisms

Approach

Make all behavior that is observable independent of the input data

Caveat

Complete independence is not always achievable
(Algorithmic requirements, some channels hard to control)

Alternative

Remove ability to observe the given aspect

Timing channels

Blinding

- Modify data computed on in such a way that operation always takes equal time
- Requires inverse unblinding that can be performed after the operation
- Noise injection

Timing channels

Blinding

- Modify data computed on in such a way that operation always takes equal time
- Requires inverse unblinding that can be performed after the operation
- Noise injection

Branch elimination/equalisation

Removes changes in runtime due to different operations depending on data

Example: Move different data processed in different branch targets to same cacheline

Timing channels

Blinding

- Modify data computed on in such a way that operation always takes equal time
- Requires inverse unblinding that can be performed after the operation
- Noise injection

Branch elimination/equalisation

Removes changes in runtime due to different operations depending on data

Example: Move different data processed in different branch targets to same cacheline

Prevent statistical analysis

Avoid running the same algorithm on attacker observable data multiple times.

Challenge-response is prone to this!

Page-Fault Channel / Fault channels

Detection

- Given a reliable time-source constant page-faults can be detected as unusually long program runtime
- SGX v2 can notify the protected program of page-faults. It may chose not to compute on secret data if such page-faults come unexpected

Page-Fault Channel / Fault channels

Detection

- Given a reliable time-source constant page-faults can be detected as unusually long program runtime
- SGX v2 can notify the protected program of page-faults. It may chose not to compute on secret data if such page-faults come unexpected

Prevention

- Don't use paging. Require all memory to be mapped
- Avoid dynamic allocation of shared resources

Meltdown / Spectre

Meltdown

- KPTI - Kernel Page Table Isolation
- HW: Don't speculate across protection boundarys

Meltdown / Spectre

Meltdown

- KPTI - Kernel Page Table Isolation
- HW: Don't speculate across protection boundaries

Spectre

- Speculation fences

Power / Acoustic / EM

Power Channel

- Use internal power source or high-capacitance in power path for sensitive instructions (low pass effect)
- Use same-complexity instructions for input-dependent code (mul instead of shift)

Power / Acoustic / EM

Power Channel

- Use internal power source or high-capacitance in power path for sensitive instructions (low pass effect)
- Use same-complexity instructions for input-dependent code (mul instead of shift)

Acoustic

- Counter-noise to mask real typing
- Avoid typing sensitive information (on-screen keyboard)

Power / Acoustic / EM

Power Channel

- Use internal power source or high-capacitance in power path for sensitive instructions (low pass effect)
- Use same-complexity instructions for input-dependent code (mul instead of shift)

Acoustic

- Counter-noise to mask real typing
- Avoid typing sensitive information (on-screen keyboard)

Electro Magnetic Radiation

- Use EM shielding on chips
- Use EM shielding for case

Data remanence

Zero memory

- Like really zero it! (`memset_s` for C11, `SecureZeroMemory` for Windows)

Data remanence

Zero memory

- Like really zero it! (memset_s for C11, SecureZeroMemory for Windows)
- Remember copies of the data! (Stack? Heap?)

Data remanence

Zero memory

- Like really zero it! (`memset_s` for C11, `SecureZeroMemory` for Windows)
- Remember copies of the data! (Stack? Heap?)
- Not all copies are immediately obvious! Compilers may create additional ones

Data remanence

Zero memory

- Like really zero it! (`memset_s` for C11, `SecureZeroMemory` for Windows)
- Remember copies of the data! (Stack? Heap?)
- Not all copies are immediately obvious! Compilers may create additional ones
- And of course you remembered the XMM registers, right?

Data remanence

Zero memory

- Like really zero it! (`memset_s` for C11, `SecureZeroMemory` for Windows)
- Remember copies of the data! (Stack? Heap?)
- Not all copies are immediately obvious! Compilers may create additional ones
- And of course you remembered the XMM registers, right?

Data remanence

Zero memory

- Like really zero it! (memset_s for C11, SecureZeroMemory for Windows)
- Remember copies of the data! (Stack? Heap?)
- Not all copies are immediately obvious! Compilers may create additional ones
- And of course you remembered the XMM registers, right?

Cold Boot

- Combined with the above very hard! Use shut down and not hibernate / suspend. After a few seconds you should be fine.
- Idea: Write secret data to physical 0x7c00 - 0x7dFF! MBR is loaded there :)

Summary

Sidechannels

... are unintended information sources for extracting secret data

Summary

Sidechannels

... are unintended information sources for extracting secret data

Attacks

There are a plethora of side-channels in every normal system! We only touched on a few methods! Your imagination is the limit.

Summary

Sidechannels

... are unintended information sources for extracting secret data

Attacks

There are a plethora of side-channels in every normal system! We only touched on a few methods! Your imagination is the limit.

Defense

... is very hard. The best way is to design algorithms from the ground up with side-channels in mind!

Overview

- <http://csrc.nist.gov/groups/STM/cmvp/documents/fips140-3/physec/papers/physecpaper19.pdf>

Cache Side-Channels

- <https://www.usenix.org/system/files/conference/usenixsecurity14/sec14-paper-yarom.pdf>

Page-fault Channel

- <http://www.ieee-security.org/TC/SP2015/papers-archived/6949a640.pdf>
- <https://www.usenix.org/system/files/conference/atc17/atc17-hahnel.pdf>

Microarchitectural Channels

- <https://meltdownattack.com/meltdown.pdf>
- <https://spectreattack.com/spectre.pdf>

Acoustic Channels

- http://people.eecs.berkeley.edu/~tygar/papers/Keyboard_Acoustic_Emanations_Revisited/ccs.pdf

Cold Boot

- https://www.usenix.org/event/sec08/tech/full_papers/halderman/halderman.pdf

Remanence

- <http://www.daemonology.net/blog/2014-09-04-how-to-zero-a-buffer.html>
- <http://www.daemonology.net/blog/2014-09-06-zeroing-buffers-is-insufficient.html>

Defense

- https://www.blackhat.com/presentations/bh-usa-08/McGregor/BH_US_08_McGregor_Cold_Boot_Attacks.pdf
- http://fc16.ifca.ai/preproceedings/21_Anand.pdf
- <https://www.semanticscholar.org/paper/Software-mitigations-to-hedge-AES-against-cache-Brickell-Graunke/11c6fddeff9e2f95c8cf238ea9f12f8ffae7cf8c/pdf>
- <https://www.cc.gatech.edu/~slee3036/papers/shih:tsgx.pdf>